

Dolby IMS3000 Software v3.4.11 Accumulated Updates Hotfix v1.0.0

Release Notes

3 September 2020 IMS.RN.005964.DRM Issue 1

1 Introduction

This documentation provides the installation instructions and release notes for the Dolby IMS3000 software v3.4.11 accumulated hotfix v1.0.0.

Contacting Dolby

Contact Dolby Cinema Solutions and Support

- Send an email to cinemasupport@dolby.com.
- Call:

Americas: +1-415-645-4900 Europe/Middle East/Africa (EMEA): +44-33-0808-7700 Asia-Pacific (APAC): +86-400-692-6780 Japan: +81-3-4540-6782

Access documentation

Visit https://customer.dolby.com.

Submit feedback about this documentation

Send an email to documentation@dolby.com.

2 Installing the software hotfix package

You can install the software hotfix package using the **Ingest Manager** feature, a Universal Serial Bus (USB) flash drive, or File Transfer Protocol (FTP).

- Installing the hotfix package using the Ingest Manager
- Installing the hotfix package using a USB flash drive
- Installing the hotfix package using FTP

2.1 Installing the hotfix package using the Ingest Manager

You can install the software hotfix package using the Ingest Manager Upload.

Prerequisites

You have received the hotfix package from Dolby.

Procedure

- 1. From the Dolby IMS3000 web user interface (UI) menu, click Ingest.
- 2. Click Upload.
- 3. Click Choose Files.
- 4. In the window that appears, click the hotfix package to upload.
- 5. Click Upload.

If the file was uploaded successfully, this message appears: Files uploaded successfully. Click here to reboot.

Results

The Dolby IMS3000 reboots and then applies the update.

2.2 Installing the hotfix package using a USB flash drive

You can install the software hotfix package using a USB flash drive.

Prerequisites

You have received the hotfix package from Dolby.

Procedure

- 1. Insert the USB flash drive containing the hotfix package into a USB port on the Dolby IMS3000.
- 2. From the Dolby IMS3000 web UI menu, click Ingest.
- 3. In the Ingest Scan window, from the Select a Location list, select Local Storage.
- 4. Click the hotfix package.
- 5. Click Ingest.
- 6. Reboot the Dolby IMS3000 to apply the update.

2.3 Installing the hotfix package using FTP

You can install the software hotfix package using FTP.

Prerequisites

You have received the hotfix package from Dolby.

Procedure

- 1. Open an FTP client from your computer.
- 2. Enter the Dolby IMS3000 IP address. Then log in as admin.
- 3. Click the software hotifx package, and upload it to the /etc/rc.once directory.
- 4. Reboot the Dolby IMS3000 to apply the update.

3 Dolby IMS3000 accumulated updates hotfix v1.0.0 for software v3.4.11 release notes

Dolby IMS3000 accumulated updates hotfix v1.0.0 for software v3.4.11 includes other improvements. This hotfix requires the *ims3_sw_hotfix_accumulated_updates_3.4.11-1.0.0.pkg* package.

• Improvements

3.1 Improvements

Dolby IMS3000 accumulated updates hotfix v1.0.0 for software v3.4.11 includes other improvements.

Adds the ability for the Dolby IMS3000 AES-67 configuration to enable a PTP Domain of 0. This improvement grants the Dolby IMS3000 more versatility when connecting to third party amplifiers. [DCPLYR-5995]

4 Documentation revision history

The documentation revision history lists the date, issue number, and description of all publications of the *Dolby IMS3000 Software v3.4.11 Accumulated Updates Hotfix v1.0.0 Release Notes*.

Date	Issue	Description
03 September 2020	1	Release notes added for accumulated updates software hotfix v3.4.11-1.0.0

Glossary

FTP

File Transfer Protocol. A network-based protocol designed for transferring data using a client-server architecture.

USB

Universal Serial Bus. A standard that defines the cables, connectors, and communications protocols used in connections between computers and electronic devices.

UI

User interface.

Notices

Copyright

[©] 2020 Dolby Laboratories. All rights reserved.

Dolby Laboratories, Inc.

1275 Market Street San Francisco, CA 94103-1410 USA Telephone 415-558-0200 Fax 415-645-4000 http://www.dolby.com

Trademarks

Dolby and the double-D symbol are registered trademarks of Dolby Laboratories.

The following are trademarks of Dolby Laboratories:

Dialogue Intelligence[™] Dolby Theatre[®] Dolby® Dolby Vision[®] Dolby Advanced Audio[™] Dolby Vision IQ[™] Dolby Atmos[®] Dolby Voice[®] Dolby Audio[™] Feel Every Dimension[™] Feel Every Dimension in Dolby[™] Dolby Cinema[®] Dolby Digital Plus[™] Feel Every Dimension in Dolby Atmos[™] Dolby Digital Plus Advanced Audio[™] MLP Lossless[™] Dolby Digital Plus Home Theater[™] Pro Logic[®] Dolby Home Theater[®] Surround EX

All other trademarks remain the property of their respective owners.

Patents

THIS PRODUCT MAY BE PROTECTED BY PATENTS AND PENDING PATENT APPLICATIONS IN THE UNITED STATES AND ELSEWHERE. FOR MORE INFORMATION, INCLUDING A SPECIFIC LIST OF PATENTS PROTECTING THIS PRODUCT, PLEASE VISIT http://www.dolby.com/patents.